

OmuxNET Optomux Software

Copyright:

Copyright (c) 2018 Douglas E. Moore
dougmo52@gmail.com

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Description:

The Optomux communications specification is contained in a document currently available at:

https://www.opto22.com/support/resources-tools/documents/1572_optomux_protocol_guide-pdf.

The OmuxNET software provides implements the Optomux communications specification in Python3.4. The OmuxNET software requires 3 files:

- OmuxNET.py – Optomux command construction and Optomux response processing
- OmuxTTL.py – Linux serial port configuration and control
- OmuxUTL.py – various functions such as logging function calls for debugging

OmuxNET.py:

This file implements an Optomux interface similar to the Opto 22 Optoware driver. That is, it maintains the concept of Optomux device addresses, Optomux module positions, Optomux command modifiers, and Optomux Information data exchange similar to the Optoware Send_Receive_Optomux driver function.

OmuxNET actually wraps the 80 or so Optoware driver command numbers described in the Optomux Protocol document section 'List of Driver Commands by Number' on pp 38-40 in Python functions of a

similar name. The wrappers try as much as possible to simplify passing of positions and info and to avoid passing modifiers when the purpose of the modifier was to create a sub command.

For example, the 'Set Time Delay' function takes a character modifier from the string 'HIJK' to change the output point action between pulse and delay, low or hi. Thus 'Set Time Delay" has been split into 4 functions which avoid the need to pass a modifier as a function argument.

```
def pulse_on(self,address,positions,delay):
def delay_on(self,address,positions,delay):
def pulse_off(self,address,positions,delay):
def delay_off(self,address,positions,delay):
```

As much as is possible, the OmuxNET implementation of Optoware commands allows positions to be passed as either a tuple or bitmask, that is (0,1,2,3) or 15 should act the same.

As luck would have it, there was one Optomux command that required the module position to be passed as a hex character rather than a mask or tuple, the 'Average and Read Input' command on page 103. For some reason my B3000s return a N01\r for that command anyway as if they don't support it.

Example:

See the 'Set Output Waveform' example on 'p132 Optomux Protocol Guide' as a comparison of this software to Optoware parameter passing.

Optoware driver example to Start a continuous square wave at output points 4, 13, and 14 using the High limit is 170 (66.4% of full scale at 8.74 minutes for full-scale change x 2).

```
OMUX_Pos(0) = 4
```

```
OMUX_Pos(1) = 13
```

```
OMUX_Pos(2) = 14
```

```
OMUX_Pos(3) = -1
```

```
OMUX_Mod(0) = 6 'period is 8.74 mins
```

```
OMUX_Mod(1) = 4 'square wave
```

```
OMUX_Info(0) = 170 'high limit
```

```
OMUX_Info(1) = 0 'low limit
```

```
result = Send_Receive_Optomux(OMUX_Handle, 43, OMUX_Pos(0), _
    OMUX_Mod(0), OMUX_Info(0), OMUX_TimeOut)
```

OmuxNET would handle this using:

```
def set_output_waveform(self,address,positions,rate,shape, hi_limit,lo_limit):
```

It could be called with either a positions tuple or a positions bitmask:

- `set_output_waveform(43,(4,13,14),6,4,170,0)`
- `set_output_waveform(43,0x6010,6,4,170,0)`

Known issues:

- My B3000s don't seem to generate an analog square wave in response to either the 'Enhanced Output Waveform' or 'Set Output Waveform' command even though they ACK it as being a valid command. All of the other waveforms work.
- The 'Average and Read Input' command is NAK'd as being unsupported. This is true even though I send the exact ASCII Optomux message in the example on p103 of the users guide.
- If I connect an Analog 10V output to an analog +/-10 V input, I can emulate temperature inputs and compute a temperature using the equations from the section 'Converting Temperature Readings' starting on page 155 if I use the 'Read Analog Inputs' or 'Read Averaged Inputs' commands.
- The B3000 unexpectedly changes the value returned by 'Read Analog Inputs' from an analog module when the module is set as a temperature input using the command 'Set Temperature Probe Type'. I have no analog temperature modules for testing the 'Read Temperature Inputs' and 'Read Average Temperature Inputs' so it would be a surprise if I am converting the Optomux data to a correct temperature reading.

OmuxTTY:

OmuxTTY contains declarations and functions to handle configuring, opening, closing, reading, and writing the serial ports in a Linux environment. It is likely that OmuxNET would work on other platforms if OmuxTTY was ported to the target platform. I wanted the Linux Python experience.

OmuxUTL:

Predominately involved in wrapping functions to allow debugging calls.

- `utl.start_logging()` - turns on logging
- `utl.stop_logging()` - turns off logging

There is also a RangeList class that is used in the functions that implement the temperature linearization tables in the Optomux Protocol Guide.

Simple example of use:

In a bash terminal, run by typing:
`python3.4 -i OmuxNET.py`

At the bottom of the file OmuxNET.py there is a `__main__` which shows how to list serial ports, choose a baud rate, open a port, and send commands such as `power_up_clear` or `get_optomux_type`.

In the example, the Optomux network is opened, and all 256 addresses are pinged with a `power_up_clear`. Any that return a response are added to a list of devices, and they are queried with `get_optomux_type`.